

Как да влезеш в AmirchoServer

Minecraft Java 1.20.1 с Forge и модовете на сървъра. Отнема около 5 минути.

Адрес на сървъра

ElKusaCrib.duckdns.org

Изтегли инсталатора

Какво ти трябва

- Компютър с Windows, macOS или 64-битов Linux
- Minecraft Java Edition с какъвто и да е лаунчер: официалния Minecraft Launcher, TLauncher или SKLauncher
- Около 4 GB свободна RAM за играта
- Инсталаторът за твоята система от elkusacrib.duckdns.org/install: `.exe` за Windows, `.zip` за Mac или `.AppImage` за Linux

Инсталиране

1

Затвори Minecraft

Затвори играта и лаунчера, ако са отворени.

2

Пусни инсталатора

Windows

Отвори `AmirchoServer-Setup.exe`. Ако се появи „Windows protected your PC“, натисни **More info** и после **Run anyway**.

Mac

Разархивирай `AmirchoServer-Mac.zip` и отвори **AmirchoServer**. Ако Mac откаже, отвори **System Settings** → **Privacy & Security**, слез надолу и натисни **Open Anyway**.

Linux

Десен бутон върху `AmirchoServer-x86_64.AppImage` → **Properties** → разреши **Run as a program**, после го отвори с двоен клик.

Предупрежденията се появяват, защото инсталаторът не е подписан с платен сертификат.

3

Следвай стъпките

Избери език, остави панката на Minecraft както е и натисни **Install** (на Windows първо **Next**). Инсталаторът изтегля Minecraft 1.20.1 и Forge, затова отнема 1–3 минути. Когато пише, че е готово, затвори го.

4

Пусни играта с Forge

Minecraft Launcher

До бутона Play избери инсталацията **AmirchoServer** и натисни Play.

TLauncher

В списъка с версии избери **1.20.1-forge-47.4.22**. В настройките сложи памет 4096 MB.

SKLauncher

Избери версията **1.20.1-forge-47.4.22** и натисни Play.

Първото пускане е по-бавно, докато се заредят моговете.

5

Влез в сървъра

Отиди в **Multiplayer**. AmirchoServer е най-отгоре в списъка, натисни **Join Server**. Ако го няма: **Add Server**, в Server Address напиши **ElKusaCrib.duckdns.org** и натисни **Done**.

6

Регистрирай се (само първия път)

Ще се отвори прозорец **Register**. Измисли парола и я напиши два пъти. Имаш 60 секунди. Следващия път само въвеждаш същата парола в прозореца **Login**.

Важно: използвай парола, която не ползваш никъде другаде. Тя не позволява на някой друг да влезе с твоето име.

Ако прозорецът не се появи, напиши в чата:

```
/register парола парола    първия път
/login парола               всеки следващ път
/changepassword стара нова  смяна на паролата
```

Гласов чат

Сървърът има Simple Voice Chat, така че можеш да говориш с играчите близо до теб.

Caps Lock задръж, за да говориш

V менюто на гласовия чат: микрофон, сила на звука, групи

Първия път играта ще пита за достъп до микрофона, позволи го. Ако в ъгъла пише, че гласовият чат не е свързан, кажи на Amir.

Какво променя инсталаторът

- Инсталира Forge 1.20.1-47.4.22.
- Добавя или обновява моговете на сървъра в папката **mods**. Твоите собствени могове (миникарта, шейдъри и гр.) остават.
- Премества в **mods-backup-дата** само по-стари версии на моговете на сървъра, могове, които сървърът вече не ползва, и могове за друга версия на Minecraft. Нищо не се изтрива.
- Добавя сървъра най-отгоре в Multiplayer, без да пипа другите ти сървъри.
- Дава на профила AmirchoServer 4 GB памет в официалния лаунчер.

Ако ти трябва нещо от резервната папка, просто го премести обратно в **mods**.

Ако нещо не стане

Mismatched mod channel list / Incompatible FML modded server

Някой мод не е точната версия, липсва или имаш излишен. Пусни инсталатора отново.

Connection timed out / Can't connect to server

Сървърът може да е спрял или адресът да се е сменил. Питай Amir.

Играта забива или се срива при зареждане

Дай ѝ 4 GB памет (в TLauncher от настройките) и затвори Chrome и други тежки програми.

Инсталаторът пише „Forge не се инсталира“

Провери интернета и го пусни пак. Ако продължава, прати на Amir снимка на прозореца.

Мас пише, че приложението е повредено или не може да се отвори

Отвори Terminal и напиши `xattr -cr ~/Downloads/AmirchoServer.app` (или пътя, където е приложението), после го отвори пак.

AppImage не се отваря на Linux

В терминала: `chmod +x AmirchoServer-x86_64.AppImage` и после `./AmirchoServer-x86_64.AppImage`.
Грешката, която излезе, прати на Amir.

Minecraft 1.20.1 · Forge 47.4.22

How to join AmirchoServer

Minecraft Java 1.20.1 with Forge and the server's mods. Takes about 5 minutes.

Server address

ElKusaCrib.duckdns.org

[Download the installer](#)

What you need

- A computer with Windows, macOS or 64-bit Linux
- Minecraft Java Edition with any launcher: the official Minecraft Launcher, TLauncher or SKLauncher
- About 4 GB of free RAM for the game
- The installer for your system from elkusacrib.duckdns.org/install: `.exe` for Windows, `.zip` for Mac or `.AppImage` for Linux

Install

1 Close Minecraft

Close the game and the launcher if they're open.

2 Run the installer

Windows

Open `AmirchoServer-Setup.exe`. If you see “Windows protected your PC”, click **More info**, then **Run anyway**.

Mac

Unzip `AmirchoServer-Mac.zip` and open **AmirchoServer**. If the Mac refuses, open **System Settings** → **Privacy & Security**, scroll down and click **Open Anyway**.

Linux

Right-click `AmirchoServer-x86_64.AppImage` → **Properties** → allow **Run as a program**, then double-click it.

The warnings show up because the installer isn't signed with a paid certificate.

3 Click through it

Pick your language, leave the Minecraft folder as it is and click **Install** (on Windows, **Next** first). It downloads Minecraft 1.20.1 and Forge, so it takes 1–3 minutes. When it says it's done, close it.

4 Start the game with Forge

Minecraft Launcher

Next to the Play button, choose the **AmirchoServer** installation and press Play.

TLauncher

Pick `1.20.1-forge-47.4.22` from the version list. In settings, set memory to 4096 MB.

SKLauncher

Select the `1.20.1-forge-47.4.22` version and press Play.

The first start is slower while the mods load.

5

Join the server

Go to **Multiplayer**. AmirchoServer is at the top of the list; click **Join Server**. If it isn't there: **Add Server**, type `ElKusaCrib.duckdns.org` as the Server Address and click **Done**.

6

Register (first time only)

A **Register** window opens. Choose a password and type it twice. You have 60 seconds. Next time you just type the same password into the **Login** window.

Important: use a password you don't use anywhere else. It's what stops anyone else from joining as you.

If the window doesn't appear, type in chat:

```
/register password password    the first time
/login password                  every time after that
/changepassword old new         to change your password
```

Voice chat

The server has Simple Voice Chat, so you can talk to players near you.

Caps Lock hold to talk

V the voice chat menu: microphone, volume, groups

The first time, the game asks for microphone access; allow it. If a corner icon says voice chat isn't connected, tell Amir.

What the installer changes

- Installs Forge 1.20.1-47.4.22.
- Adds or updates the server's mods in your `mods` folder. Your own mods (minimap, shaders and so on) stay.
- Moves to `mods-backup-date` only older versions of the server's mods, mods the server no longer uses, and mods for a different Minecraft version. Nothing is deleted.
- Adds the server to the top of Multiplayer without touching your other servers.
- Gives the AmirchoServer profile 4 GB of memory in the official launcher.

If you need something from the backup folder, just move it back into `mods`.

If something goes wrong

Mismatched mod channel list / Incompatible FML modded server

A mod is the wrong version, missing, or extra. Run the installer again.

Connection timed out / Can't connect to server

The server may be off, or the address may have changed. Ask Amir.

The game freezes or crashes while loading

Give it 4 GB of memory (in TLauncher, in settings) and close Chrome and other heavy programs.

The installer says “Forge didn't install”

Check your internet and run it again. If it keeps happening, send Amir a screenshot of the window.

Mac says the app is damaged or can't be opened

Open Terminal and type `xattr -cr ~/Downloads/AmirchoServer.app` (or wherever the app is), then open it again.

The AppImage won't start on Linux

In a terminal: `chmod +x AmirchoServer-x86_64.AppImage`, then `./AmirchoServer-x86_64.AppImage`. Send Amir whatever error it prints.

Minecraft 1.20.1 · Forge 47.4.22